


Removing the Automox Agent

Depending on your operating system, there are different steps to remove the Automox Agent from your device.

Removing the Agent Using the Console (Recommended)

You can remove the agent by going to the Devices page. Using the console to remove the agent is the recommended method. For details, see [Managing Devices](#).



To manually remove the Automox agent from a device, you must follow the steps specific to your operating system.


Removing the Agent for Apple macOS

1. Open a terminal.
2. Run the following commands:


```
sudo launchctl unload /Library/LaunchDaemons/com.automox.agent.plist  
  
sudo /usr/local/bin/amagent --deregister  
  
sudo rm -f /usr/local/bin/amagent  
  
sudo rm -rf "/Library/Application Support/Automox/"
```

Removing the Agent for Microsoft Windows


- Go to *Local Services* and stop the agent.



- Open a command prompt in Administrator mode and deregister the Automox agent.



- Uninstall the agent.



Removing the Agent for Debian-based Linux Operating Systems

1. Open a terminal.
2. Run the following commands:

```
sudo service amagent stop

sudo /opt/amagent/amagent --deregister

sudo apt-get remove amagent
```

Removing the Agent for SLES/SuSE and RedHat-based Linux Operating Systems (SLES, RedHat, CentOS, Amazon Linux, Fedora):

1. Open a terminal.
2. Run the following commands:

```
sudo service amagent stop

sudo /opt/amagent/amagent --deregister

sudo rpm -qa | grep amagent

sudo rpm -e amagent-1.0-19.x86_64 # (for example, should match what previous command returns)
```

Reinstalling the Automox Agent

To reinstall the Automox agent, ensure that the agent has first been deregistered and then removed.

1. Deregister the agent. See [Deregistering the agent](#).
 2. Remove the agent, as described here.
 3. Follow the instructions in [Installing the Automox Agent](#).
-